2019/6/28更新

2.2. Email client setting IMAP（Thunderbird-Current TUMail)

In this item, we will explain the setting method that can be received by IMAP with email client.

If you set up to receive both new and current TUMail, email will be sent to both during 6 / 17-7 / 31.

2.2　Email client setting

2.2.1　IMAP reception setting(Thunderbird-Current TUMail)


2.2 Email client setting

2.2.1 IMAP reception setting(Thunderbird-Current TUMail)


In this section, we will explain how to add a new TUMail (Gmail) account with IMAP settings in the email client Thunderbird.

2.2.1IMAP reception setting(Thunderbird-Current TUMail)


1. Click Account Settings on the Tools tab.



2. Click "Add Email Account" in "Account Operation".




3. Enter "Display name when sending", email address and password for "Your name", and click "Continue".



Password :
Tohokudai ID password

4. Since the screen you are searching for is displayed, click "Manual setting" without waiting for the search results.



5. The following screen is displayed.



6. Set Incoming Server and Outgoing Server as follows, set "Email Address“ for Incoming Server and Outgoing Server for "User Name", and click "Retest".



Name : Sender Display Name
Email address :
TUMail address

Password :
Tohokudai ID password

Incoming sever
「IMAP」
「mail.tohoku.ac.jp」
「993」
「SSL/TLS」
「Normal password authentication」

Outgoing server :
「mail.tohoku.ac.jp」
「465」
「SSL/TLS」
「Normal password authentication」

User Name :
Tohokudai ID

2.2. Email client setting (IMAP)

In this item, we will explain the setting method that can be received by IMAP with email client. The manual "1.4 POP / IMAP permission setting" needs to be done in advance.

If you set up to receive both new and current TUMail, email will be sent to both during 6 / 17-7 / 31.

2.2 Email client setting

2.2.1 IMAP reception setting


2.2.3 How to set mailing list address as sender

2.2. Email client setting
2.2.1. IMAP reception setting


In this section, we will explain how to add a new TUMail (Gmail) account with IMAP settings in the email client Thunderbird.
The manual "1.4 POP / IMAP permission setting" needs to be set in advance.

2.2.1. IMAP reception setting


1. Click “Account Settings” on the Tools tab.




2. Click "Add Mail Account" in "Account Action".




3. Enter "Display name when sending" in "Your name" and "Email address" enter the password set in "1.1 Login to New TUMail" in the manual for the address password of TUMail, and click "Continue".




4. If the "Email Address" and "Password" are entered, the following screen will be displayed. Click "Finish".




5. If the settings are incorrect or not found successfully, the following screen will be displayed.




6. Set Incoming Server and Outgoing Server as follows, set TUMail Address for Incoming Server and Outgoing Server for "Username", and click "Re-test".




7. "The following settings were found by probing the given server." Is displayed, Select Authentication and click “Done".




8. Confirm that your TUMail address has been added.




9. Set the disk space as follows in "Synchronization & Storage".




10. Confirm that it has been rewritten, and click “Outgoing Server(SMTP)".




11. Select the one for added TUMail, and click "Set default".




12. Confirm that the default have been switched.




13. Select your own Tohokudai ID and click “Remove".



14. A confirmation screen will be displayed. Click "Yes".




15. Confirm that your Tohokudai ID has been deleted.




If current TUMail receiving setting is POP, please set to turn off POP reception according to the items on the following pages.
If the current TUMail receiving setting is IMAP, refer to the manual "3.1 Data Migration Method Using email client", and do data migration and deletion of current TUMail settings.


16. Click "Account Settings" under "Tools".



17. Check off the "Server Settings".



18. Confirm that the check is off, and click "OK".



°

3. Data migration (Thunderbird→TUMail(Gmail)

In this section, we will explain how to import the email data of the former TUMail into the New TUMail.

Current TUMail data is not migrated. If you need current TUMails, you need to migrate data on your own.


【Note】
The current TUMail server will be discontinued in mid-December, 2019. After that, if you do not migrate current email data, you will not be able to view current email data.

3. Data migration

3.1 Data migration using email software

This item explains how to migrate current email data received by email client to New TUMail. The transition pattern in red frame is the target of this migration process.

・It is necessary to set the manual "2.2.1 IMAP reception setting" in advance.
・ If an error occurs during migration, the email data may be lost. This section explains how to delete the original data after checking the copied email data.




3.1 Data migration using email software


1. Start Thunderbird.

Current TUMail IMAP

New TUMail IAMP




2. Select your inbox and select the data to be migrated. * All data can be selected by clicking "Edit" "Select" "All".
※ If there is a large amount of data, an error or time may be required. Therefore, divide the program into 500 cases several times.
※ If you want to migrate the data of other folders, please follow the same procedure in 2. ~ 5.




Please select migration data up to 6/16. If not selected, email data will be duplicated at the migration destination.

3. Confirm that the message has been selected.




4. Specify the destination folder in "Copy to" on the "Message" tab.



A copy of the email will be implemented. It takes about 50 times per minute.


5. Confirm that email data has been copied to the migration destination.




※Folder settings are managed as tags in New TUMail.

6. If you want to migrate the data of other folders, please follow the same procedure from 2 to 5.
If migration of all folders is completed, please delete the current IMAP settings according to the item number on the next page.


7. The current TUMail account information and the New TUMail account information are both registered, please delete the current TUMail account information. Click "Account Settings" under "Tools".



8. After selecting the account settings of the former TUMail (Gmail), click “Remove Account" under "Account Action".



9. Check “Remove message data" and click “Remove".



10. Click "OK".



11. Make sure that the current TUMail setting has disappeared and that the New TUMail setting has b

