2.2. Email client setting (IMAP)

In this item, we will explain the setting method that can be received by IMAP with email client. The manual "1.4 POP / IMAP permission setting" needs to be done in advance.

If you set up to receive both new and current TUMail, email will be sent to both during 6 / 17-7 / 31.

2.2 Email client setting


2.2.1 IMAP reception setting

2.2.3 How to set mailing list address as sender


2.2. Email client setting
2.2.1. IMAP reception setting

In this section, we will explain how to add a new TUMail (Gmail) account with IMAP settings in the email client Thunderbird.
The manual "1.4 POP / IMAP permission setting" needs to be set in advance.


1. Click “Account Settings” on the Tools tab.



2. Click "Add Mail Account" in "Account Action".




3. Enter "Display name when sending" in "Your name" and "Email address" enter the password set in "1.1 Login to New TUMail" in the manual for the address password of TUMail, and click "Continue".




Password :
Set in the manual "1.1 Login to TUMail"
※The 16-digit specification specified in the manual "1.6 App Password Settings" when setting 2-step authentication


4. If the "Email Address" and "Password" are entered, the following screen will be displayed. Click "Finish".




5. If the settings are incorrect or not found successfully, the following screen will be displayed.




6. Set Incoming Server and Outgoing Server as follows, set TUMail Address for Incoming Server and Outgoing Server for "Username", and click "Re-test".




7. "The following settings were found by probing the given server." Is displayed, Select Authentication and click “Done".




8. Confirm that your TUMail address has been added.




9. Set the disk space as follows in "Synchronization & Storage".




10. Confirm that it has been rewritten, and click “Outgoing Server(SMTP)".




11. Select the one for added TUMail, and click "Set default".




12. Confirm that the default have been switched.




13. Select your own Tohokudai ID and click “Remove".



14. A confirmation screen will be displayed. Click "Yes".




15. Confirm that your Tohokudai ID has been deleted.




If current TUMail receiving setting is POP, please set to turn off POP reception according to the items on the following pages.
If the current TUMail receiving setting is IMAP, refer to the manual "3.1 Data Migration Method Using email client", and do data migration and deletion of current TUMail settings.


16. Click "Account Settings" under "Tools".




17. Check off the "Server Settings".




18. Confirm that the check is off, and click "OK".




1. Click “Account Settings” on the Tools tab.



2. Click "Add Mail Account" in "Account Action".



3. Enter "Display name when sending" in "Your name" and "Email address" enter the password set in "1.1 Login to New TUMail" in the manual for the address password of TUMail, and click "Continue".



2.2. Email client setting (POP)

This item explains how to set up POP reception with email client.
The manual "1.4 POP / IMAP permission setting" and “1.5 Set up a client(Outlook etc.) that does not support OAuth 2.0” needs to be done in advance.

If you set up to receive both new and current TUMail, email will be sent to both during 6 / 17-7 / 31.

2.2 Email client setting


2.2.2 Email client setting (POP)

2.2.3 How to set mailing list address as sender


2.2. Email client setting
2.2.2 POP reception setting

In this section, we will explain how to change the POP settings of TUMail to the POP settings of New TUMail (Gmail) using the email client Thunderbird.
The manual "1.4 POP / IMAP permission setting" needs to be done in advance.


1. Click “Account Settings” on the Tools tab.




2. Click "Server Settings".



3. The server name "mail.tohoku.ac.jp" is also changed to "pop.gmail.com". The user name is changed to “TUMail address”.




4. Confirm that it has been rewritten, and click “Outgoing Server (SMTP) ".




For details, please click following URL and see section of “I want to download emails on multiple email clients”　https://support.google.com/mail/answer/7104828?hl=en


5.　Select your Tohokudai ID and click "Edit".



6. The server name "mail.tohoku.ac.jp" is changed to "smtp.gmail.com".
Change the user name "(Tohokudai ID)" to "(TUMail Address)".




7. Confirm that you have rewritten, and click "OK."




If two-step authentication is set, “Normal password” is selected. If two-step authentication is not set, “OAuth2” is selected.


8. Click "OK".



9. Click “Get messages".



10. Make settings as follows, and click “OK".



check

Password :
Set in the manual "1.1 Login to TUMail"
※The 16-digit specification specified in the manual "1.6 App Password Settings" when setting 2-step authentication

2.2. Email client setting (Thunderbird)
2.2.3 How to set sender as mailing list address


This section explains how to set up a group mail address as a sender in the email client Thunderbird.

“2.2.1 IMAP reception setting”or”2.2.2 POP reception setting” needs to be done in advance in the manual.
The setting on the Gmail side is also required in the manual "2.1.4 How to set up group mail".


Please make settings according to this manual also when sending from “alias address”. Also in this case, the manual "2.2.1 IMAP reception setting" or "2.2.2 POP reception setting" needs to be set.
The setting on the Gmail side is also required in the manual "2.1.4 How to set up group mail".

2.2.3 How to set sender as mailing list address(Thunderbird)


1. Start Thunderbird and click "Account Settings" from "Tools".




2. Click "Manage identities Information" from the "Account Settings" screen.



3. From "Manage identities Information" , click “Add”.



4. Set as below and click "OK".



5. Confirm that it has been added.

