2.2. Email client setting (IMAP)

In this item, we will explain the setting method that can be received by IMAP with email client. The manual "1.4 POP / IMAP permission setting" needs to be done in advance.

2.2 Email client setting

2.2.1 IMAP reception setting


2.2.2 Email client setting (POP)

2.2. Email client setting
2.2.1. IMAP reception setting

In this section, we will explain how to add a new TUMail (Gmail) account with IMAP settings in the email client Outlook for Mac.
The manual "1.4 POP / IMAP permission setting" needs to be set in advance.

2.2.1. IMAP reception setting


1. Click “Tools”.




2. Click “Accounts”.




3. Click “+”, and click “New Account”.




4. Enter your TUMail address, and click “Continue”.




5. The following screen will be displayed. Wait about 30 seconds.




6. Check your TUMail address, and click “Next”.




7. Enter the password set in "1.1 Login to New TUMail" in the manuall, and click "Continue".




8. Click “Allow”.




9. Click “Allow”.



10. Click “Done”.



11. Confirm that your TUMail address has been added.



2.2. Email client setting (POP)

This item explains how to set up POP reception with email client.
The manual "1.4 POP / IMAP permission setting" needs to be done in advance.

If you set up to receive both new and current TUMail, email will be sent to both during 6 / 17-7 / 31.

2.2 Email client setting


2.2.2 Email client setting (POP)

2.2. Email client setting
2.2.2 POP reception setting


In this section, we will explain how to change the POP settings of TUMail to the POP settings of New TUMail (Gmail) using the email client Outlook for Mac.
The manual "1.4 POP / IMAP permission setting" needs to be done in advance.

2.2.2 Email client setting (POP)


1. Click “Tools”.




2. Click “Accounts”.




3. Click “+”, and click “New Account”.




4. Enter your TUMail address, click “Continue”.




5. Click “Not Gmail?”.
（This message disappears in about 2 to 30 seconds.）



6. Click “IMAP/POP”.



7. Set each item as follows, click “Add Account”.



Type： POP

Email Address :
TUMail address


Username :
TUMail address

Password :
the password set in “1.1 Login to New TUMail” in the manual


Incoming Server :
pop.gmail.com
995

Outgoing Server :
smtp.gmail.com
465

8. Check your TUMail address, and click “Next”.




9. Enter the password, and click “Next”.




the password set in “1.1 Login to New TUMail” in the manual


10. Click “Allow”.



11. Click “Allow”.



12. Click “Done”.



13. Confirm that your TUMail address has been added.

